
Segno Documentation

Release

Author

February 01, 2017

1	QR Code creation from the command line	3
1.1	Usage	3
1.1.1	Version	3
1.1.2	Error correction level	3
1.1.3	QR Code serialization	4
1.1.4	Scaling QR Codes	4
1.1.5	Changing the size of the quiet zone	4
1.1.6	Colors	4
2	Creating QR Codes or Micro QR Codes	5
2.1	Version	6
2.2	Error Correction Level	6
2.3	Data Masking	6
3	Special QR Code factory functions	7
3.1	Create a QR Code for a WIFI configuration	7
3.2	Create a QR Code encoding geographic information	7
3.3	Creating a QR Code encoding contact information	8
3.3.1	MeCard	8
3.3.2	vCard	8
4	Colors	11
5	QR Code and Micro QR Code serialization	13
6	Comparison of Python QR Code libraries	15
6.1	Features	15
6.2	Performance	16
6.2.1	Create a QR Code	16
6.2.2	Create a QR Code and serialize it as SVG	16
6.2.3	Create a QR Code and serialize it as PNG	16
7	Replace existing QR Code libs with Segno	17
8	Writing plugins for Segno	19
8.1	Simple plugin	19
9	Segno package	21
9.1	Module contents	21

9.2	High level QR Code factories	28
10	Segno's low level API	35
10.1	segno.encoder	35
10.2	segno.writers	36
11	Indices and tables	43
	Python Module Index	45

Segno generates QR Codes and Micro QR Codes according to ISO/IEC 18004:2015 (E). Aside from other Python QR Code generators, Segno has no 3rd party dependencies and is very simple to use.

Contents:

QR Code creation from the command line

The command line script “segno” can be used to print QR Codes to the terminal or to save them as file (SVG, PNG, EPS, ...).

By default, the script does not create Micro QR Codes, use `--micro` to allow the creation of Micro QR Codes or specify the version (like `--version=M3`) to create a Micro QR Code.

1.1 Usage

Output the QR Code to the terminal:

```
$ segno "Little wing"
```

Same content, but as Micro QR Code (M4):

```
$ segno "Little wing" --micro
```

1.1.1 Version

If the `version` parameter is not provided, Segno chooses the minimal version for the QR Code automatically. The version may be specified as integer or as Micro QR Code identifier.

The content ‘Layla’ would fit into a version 1 QR Code, but the following command enforces version 5:

```
$ segno "Layla" --version=5
$ segno "Layla" -v=5
```

Micro QR Code:

```
$ segno "Layla" -v=m4
$ segno "Layla" --version=M4
```

1.1.2 Error correction level

The default error correction level is “L”, use the `error` parameter to change it:

```
$ segno "Ain't no grave" --error=q
$ segno "Heart of Gold" -e=h
```

1.1.3 QR Code serialization

Printing the QR Codes to the terminal is nice but the `output` parameter serializes the QR Code in one of the supported file formats:

```
$ segno "White Room" --output=white-room.png
$ segno "Satellite Of Love" -o=satellite.svg
$ segno "Mrs. Robinson" --output=mrs.eps
$ segno "De Do Do Do, De Da Da Da" --output=dedodo.pdf
$ segno "Tin Pan Alley" --output=tin-pan-alley.svgz
$ segno "The Thrill Is Gone" --output=thrill-gone.txt
```

1.1.4 Scaling QR Codes

If the resulting QR Code is too small, `scale` can be used to create a more appropriate output:

```
$ segno "Money Talks" --scale=10 --output=money-talks.png
```

If the serializer does not support a scaling factor (i.e. text output), this parameter is ignored.

1.1.5 Changing the size of the quiet zone

The generated QR Codes will have a recommended quiet zone / border around the symbol. To change the size of the border, `border` can be utilized:

```
$ segno "Black Magic Woman" --border=0 --output=black-magic-woman.svg
$ segno "Shine On You Crazy Diamond" --border=10 --output=diamond.png
```

1.1.6 Colors

Usually, all QR Codes are serialized in black and white. Use `color` to change the color of the dark modules and `background` to change the color of the light modules. If the color or background should be transparent, set the value to "transparent":

```
$ segno "So Excited" --color=darkblue --output=excited.png
$ segno "Hotel California" --background=transparent --output=hotel.png
$ segno "Don't Give Up" --color=transparent --output=dontgiveup.svg
```

If the serializer does not support `color` or `background`, these arguments are ignored.

Creating QR Codes or Micro QR Codes

Segno's (Micro) QR Codes are independent of a concrete output format; it's possible to create more than one rendering (output format) from a single QR Code or Micro QR Code:

```
>>> import segno
>>> qr = segno.make('Henry Lee')
>>> qr.save('henry-lee.svg') # SVG document
>>> qr.save('henry-lee.png') # PNG image
>>> qr.save('henry-lee.eps') # EPS document
>>> qr.save('henry-lee.txt') # Text output
```

By default, the serialized (Micro) QR Codes are black and have a quiet zone (border) of four (or two for Micro QR Codes) modules. Nearly all output methods provide options to change the color and border.

```
>>> import segno
>>> qr = segno.make('You Know My Name (Look Up The Number)')
>>> qr.save('you-know-my-name-no-border.svg', border=0) # no border / quiet zone
>>> qr.save('you-know-my-name-color-green.svg', color='green') # default border, dark modules are green
>>> qr.save('you-know-my-name-background-grey.svg', background='#eee') # default border, background is grey
```

The factory function `segno.make()` chooses the minimal possible (Micro) QR Code for the provided input.

```
>>> import segno
>>> qr = segno.make('Rain')
>>> qr.version
'M3'
```

The caller may enforce that a QR Code instead of a Micro QR Code should be generated even if the content may fit into a Micro QR Code.

```
>>> import segno
>>> qr = segno.make('Rain', micro=False)
>>> qr.version
1
```

Further, Segno provides two additional factory functions to enforce the creation of QR Codes or Micro QR Codes: `segno.make_qr()` for QR Codes and `segno.make_micro()` to create Micro QR Codes:

```
>>> import segno
>>> mqr = segno.make_micro('The Beatles') # Micro QR Code
>>> mqr.designator # Get the version and error level
'M4-M'
>>> qr = segno.make_qr('The Beatles') # Same content but as QR Code
>>> qr.designator
'1-Q'
```

If the provided content is too large, a `segno.DataOverflowError` is thrown:

```
>>> import segno
>>> qr = segno.make_micro('The Curse of Millhaven')
Traceback (most recent call last):
...
DataOverflowError: Data too large. No Micro QR Code can handle the provided data
```

2.1 Version

It's possible to specify the desired version for the provided content.

```
>>> import segno
>>> qr = segno.make('Light My Fire')
>>> qr.version
'M4'
>>> qr = segno.make('Light My Fire', version=1)
>>> qr.version
1
```

2.2 Error Correction Level

By default, Segno uses the error correction level “L” to encode the (Micro) QR Code. Use the parameter `error` to change the error correction level. The `error` parameter is case-insensitive; to specify the error correction level “L”, “l” and “L” are valid values. Available error correction levels are L (lowest error correction level), M, Q and H. The error correction level “H” is not available for Micro QR Codes, if the user specifies the error correction level “H”, a QR Code is generated by `make`, never a Micro QR Code.

```
>>> import segno
>>> qr = segno.make('Parisienne Walkways', error='l') # Explicit error correction level
>>> qr.version
2
>>> # Enhancing the error correction level may enforce another QR Code version
>>> qr = segno.make('Parisienne Walkways', error='H')
>>> qr.version
3
```

2.3 Data Masking

Segno chooses by default the optimal mask for the provided input, but the user may specify the preferred mask as well.

```
>>> import segno
>>> qr = segno.make('Ai Du')
>>> qr.mask
0
>>> qr = segno.make('Ai Du', mask=3)
>>> qr.mask
3
```

Special QR Code factory functions

The `helpers` module provides factory functions to create common QR Codes for encoding WIFI configurations, MeCards or geographic locations.

The created QR Codes use at minimum the error correction level “L”. If a better error correction level is possible without changing the QR Code version, the better error correction level will be used.

3.1 Create a QR Code for a WIFI configuration

```
>>> from segno import helpers
>>> # Create a WIFI config with min. error level "L" or better
>>> qr = helpers.make_wifi(ssid='My network', password='secret', security='WPA')
>>> qr.designator
'3-M'
```

If you want more control over the creation of the QR Code (i.e. using a specific version or error correction level, use the “`make_wifi_data`” factory function, which returns a string which encodes the WIFI configuration.

```
>>> import segno
>>> from segno import helpers
>>> config = helpers.make_wifi_data(ssid='My network', password='secret', security='WPA')
>>> config
'WIFI:T:WPA;S:My network;P:secret;;'
>>> # Create a QR Code with error correction level "L"
>>> qr = segno.make(config, error='l', boost_error=False)
>>> qr.designator
'3-L'
```

3.2 Create a QR Code encoding geographic information

```
>>> from segno import helpers
>>> latitude, longitude = 38.8976763,-77.0365297
>>> qr = helpers.make_geo(latitude, longitude)
>>> qr.designator
'2-M'
```

A factory function for encoding the geographic information as string is also available.

```
>>> import segno
>>> from segno import helpers
>>> latitude, longitude = 38.8976763, -77.0365297
>>> geo_uri = helpers.make_geo_data(latitude, longitude)
>>> geo_uri
'geo:38.8976763,-77.0365297'
>>> # Use version 4 instead of the minimum version
>>> qr = segno.make(geo_uri, version=4)
>>> qr.designator
'4-H'
```

3.3 Creating a QR Code encoding contact information

3.3.1 MeCard

The function `make_mecard` returns a QR Code which encodes contact information as MeCard.

```
>>> from segno import helpers
>>> qr = helpers.make_mecard(name='Doe,John', email='me@example.org', phone='+1234567')
>>> qr.designator
'3-L'
>>> # Some params accept multiple values, like email, phone, url
>>> qr = helpers.make_mecard(name='Doe,John', email=('me@example.org', 'another@example.org'), url=[
>>> qr.save('my-mecard.svg')
```

A factory function which returns the MeCard as string is available as well.

```
>>> import segno
>>> from segno import helpers
>>> mecard = helpers.make_mecard_data(name='Doe,John', email='me@example.org', phone='+1234567')
>>> mecard
'MECARD:N:Doe,John;TEL:+1234567;EMAIL:me@example.org;;'
>>> qr = segno.make(mecard, error='H')
>>> qr.designator
'6-H'
```

3.3.2 vCard

The function `make_vcard` returns a QR Code which encodes contact information as vCard version 3.0.

```
>>> from segno import helpers
>>> qr = helpers.make_vcard(name='Doe;John', displayname='John Doe', email='me@example.org', phone='+
>>> qr.designator
'5-L'
>>> # Some params accept multiple values, like email, phone, url
>>> qr = helpers.make_vcard(name='Doe;John', displayname='John Doe', email=('me@example.org', 'another
>>> qr.save('my-vcard.svg')
```

A factory function which returns the vCard as string is available as well.

```
>>> import segno
>>> from segno import helpers
>>> vcard = helpers.make_vcard_data(name='Doe;John', displayname='John Doe', email='me@example.org',
>>> vcard
'BEGIN:VCARD\r\nVERSION:3.0\r\nN:Doe;John\r\nFN:John Doe\r\nEMAIL:me@example.org\r\nTEL:+1234567\r\n'
```

```
>>> qr = segno.make(vcard, error='H')
>>> qr.designator
'9-H'
```

Colors

Almost all serializers support custom settings for the color of the dark modules and the background (light modules) of a (Micro) QR Code.

The color values can be provided as tuple (R, G, B) , as web color name (like 'red') or as hexadecimal #RRGGBB value (i.e. '#085A75'). If alpha transparency is supported (i.e. PNG and SVG), hexadecimal values like #RRGGBBAA are accepted.

The color values are automatically converted into a meaningful value of the specific output format (note that providing an alpha channel to a serializer which does not accept an alpha channel results into an error).

QR Code and Micro QR Code serialization

A QR Code or Micro QR Code is independent of its output, it's just a matrix. To save a QR Code or Micro QR Code, Segno provides several output formats.

Segno provides a `segno.QRCode.save()` method to serialize the (Micro) QR Code in different formats:

```
>>> import segno
>>> qr = segno.make('Polly')
>>> qr.save('polly.svg')
>>> qr.save('polly.png')
>>> qr.save('polly.eps')
```

All serializers accept a `border` parameter which indicates the “quiet zone” of a (Micro) QR Code. If `border` is `None`, the default border (quiet zone) size will be used. If the resulting (Micro) QR Code should have no border or a custom border, you may specify the border

```
>>> import segno
>>> qr = segno.make('Vampire Blues')
>>> qr.save('vampire-blues.svg', border=0) # No border
>>> qr.save('vampire-blues.png', border=10) # Bigger border
```

Most serializers accept a `scale` parameter which indicates the scaling factor of the serialization. By default, the scaling factor is 1 which means that the dark / light modules of a (Micro) QR Code is interpreted as one unit in the specific user space (i.e. 1 pixel for the PNG serializer or 1 point (1/72 of an inch) in EPS). Some serializers (like PNG) accept only an integer value or convert the provided scaling factor to an integer. Other, like SVG and EPS, accept float values and do not “downgrade” it to an integer.

```
>>> import segno
>>> qr = segno.make_qr('The Beatles')
>>> qr.save('the-beatles.png', scale=1.2) # No scaling at all since int(1.2) is 1
>>> qr.save('the-beatles-2.png', scale=10) # 1 module == 10 pixels
>>> qr.save('the-beatles.svg', scale=1.2) # SVG accepts float values
>>> # The SVG serializer provides the "unit" parameter to specify
>>> # how to interpret the values
>>> qr.save('the-beatles-2.svg', scale=10, unit='mm') # 1 unit = 1 mm
>>> qr.save('the-beatles-2.svg', unit='cm') # 1 unit = 1 cm, result as above
```

Many serializers accept the parameters `color` and `background` to specify the color of the dark modules and light modules (background). See [Colors](#) for details.

```
>>> import segno
>>> qr = segno.make('Neil Young')
>>> qr.save('neil-young.svg', color='darkblue', background='yellow')
>>> qr.save('neil-young.png', color='#ccc')
```

```
>>> qr.save('neil-young-2.png', background=None) # Transparent background
>>> # Dark modules = transparent, light modules = black
>>> qr.save('neil-young-3.png', color=None, background='black')
>>> # Dark modules with alpha transparency
>>> qr.save('neil-young-4.png', color='#0000ffcc')
>>> qr.save('neil-young-4.svg', color='#00fc') # Same as above but SVG
>>> # Another color, save as compressed SVG
>>> qr.save('neil-young-5.svgz', color=(8, 90, 117))
```

See `segno.QRCode.save()` for a complete reference which parameters are accepted by the specific serializer.

Comparison of Python QR Code libraries

6.1 Features

Description	qrcode	PyQRCode	qrcodegen	Segno
Library license	BSD	BSD	MIT	BSD
Library version	5.3	1.2.1	1.0.0	0.2.4
Mode Numeric	Yes	Yes	Yes	Yes
Mode Alphanumeric	Yes	Yes	Yes	Yes
Mode Byte	Yes	Yes	Yes	Yes
Mode Kanji	No	Yes	No	Yes
Mode ECI	No	No	Yes	Yes
Mode FNC1	No	No	No	No
Mode Structured Append	No	No	No	No
Mixing modes	Yes	No	Yes	Yes
QR Codes version 1 - 40	Yes	Yes	Yes	Yes
Micro QR Codes version M1 - M4	No	No	No	Yes
Output acc. to ISO/IEC 18004:2015(E) Fig. 1	Yes	No	No	Yes
Output acc. to ISO/IEC 18004:2015(E) I.3.	No (not available)	No (not available)	No (not available)	Yes
Find maximal error correction level	No	No	Yes	Yes
PNG output	Yes	Yes	No	Yes
SVG output	Yes	Yes	Yes	Yes
EPS output	Yes	Yes	No	Yes
PDF output	Yes	No	No	Yes
XBM output	No	Yes	No	Yes
XPM output	No	No	No	Yes
PBM output	Yes	No	No	Yes
PAM output	No	No	No	Yes

Continued on next page

Table 6.1 – continued from previous page

Description	qrcode	PyQRCode	qrcodegen	Segno
LaTeX support	No	No	No	Yes
PNG data URI	No	kind of (not a URI)	No	Yes
SVG data URI	No	No	No	Yes
Text output	Yes	Yes	No	Yes
ANSI escape code output	Yes	Yes	No	Yes
Other output formats (i.e. JPEG)	Yes	No	No	No, but via PIL plugin
Black and white QR Codes	Yes	Yes	Yes	Yes
Colored QR Codes	No	Yes	No	Yes
Changing size of modules (scaling factor)	Yes	Yes	No	Yes
Command line script	Yes	No	No	Yes
Plugins	No	No	No	Yes
Default encoding in Byte mode	UTF-8	ISO/IEC 8859-1 or UTF-8	UTF-8	ISO/IEC 8859-1 or UTF-8
3rd party dependencies	six, Pillow or Pymaging and Pymaging-PNG (Windows: colorama)	PyPNG	•	•

6.2 Performance

Some performance indicators. The script `benchmarks.py` ran on a MacBook Air 2,13 Core2 Duo using CPython 2.7.10. Each SVG / PNG image uses a scaling factor of 10 (aside from qrcodegen which does not support any scaling).

6.2.1 Create a QR Code

Create a 1-M QR Code “QR Code Symbol”.

6.2.2 Create a QR Code and serialize it as SVG

Create a QR Code 1-M “QR Code Symbol” and serialize it as SVG document.

6.2.3 Create a QR Code and serialize it as PNG

Create a QR Code 1-M “QR Code Symbol” and serialize it as PNG image.

Replace existing QR Code libs with Segno

The sub-project [Segno Mimos](#) provides APIs which are usable to replace common Python QR Code libs like [PyQR-Code](#) and [qrcode](#) with Segno.

Writing plugins for Segno

`segno.QRCode` provides a plugin architecture which utilizes egg entry points.

All plugins must use the `segno.plugin.converter` entry point to be recognized. If a plugin is detected, the user may use the plugin by calling `to_XXX` where `XXX` refers to the plugin name.

The specific plugin is invoked by providing the `segno.QRCode` instance and any further arguments or keywords.

8.1 Simple plugin

This section explains how to write a plugin which writes to `stdout` and uses `X` for dark modules and `_` for light modules.

Content of `simple_plugin.py`:

```
import sys

def write(qrcode):
    write = sys.stdout.write
    for row in qrcode.matrix:
        for col in row:
            write('X' if col else '_')
        write('\n')
```

`setup.py`:

```
setup(
    name='simple-plugin',
    version='1.0',
    license='BSD',
    author='John Doe',
    author_email='john@example.org',
    platforms=['any'],
    py_modules=['simple_plugin'],
    entry_points="""
    [segno.plugin.converter]
    simple = simple_plugin:write
    """,
    install_requires=['segno'],
)
```

Once installed, it's possible to call this plugin via:

```
>>> import segno
>>> qr = segno.make('Chelsea Hotel No. 2')
>>> qr.to_simple()
XXXXXXXXXX_XXXX_XX_X_XXXXXXXXXX
X_____X_____X_____X_____X
X_XXX_X_XX_XXX_X_XXX_X
X_XXX_X_X_XXX_X_X_XXX_X
X_XXX_X_XX_XX_X_X_XXX_X
X_____X_X_XXX_X_X_____X
XXXXXXXXXX_X_X_X_X_X_XXXXXXXXXX
_____X_X_XX_____
X_X_XX_XXX_XXXXXX_X_X_X_X
_XX_X_XXXXXX_XX_XX_X_X
_X_____X_____X_XXXX_XX_X_X
_XX_X_XX_XXX_XXXX_XX_
_X_XXXX_XXX_XX_X_XXXX_X_
_____X_X_X_X_XXXX_XX_X
XXXXXX_X_X_XX_XX_XXXXXX_X
_____XX_XXX_X_____X_XX
XX_X_X_XXXXXX_XXXXXX_XX
_____X_X_X_X_X_____
XXXXXXXXXX_X_XXX_X_X_X_X
X_____X_X_XX_X_X_XX_XX
X_XXX_X_X_XXXXXXXXXXXX_XX
X_XXX_X_____XX_X_XX_X_
X_XXX_X_XXXX_____X_XX_XXX
X_____X_X_X_XX_X_X_
XXXXXXXXXX_XXXXXX_X_XXXX_X
```

Segno package

9.1 Module contents

QR Code and Micro QR Code implementation.

“QR Code” and “Micro QR Code” are registered trademarks of DENSO WAVE INCORPORATED.

exception `segno.QRCodeError`

Generic QR Code error.

exception `segno.ErrorLevelError`

Indicates errors related to QR Code error correction level.

exception `segno.ModeError`

Indicates errors related to QR Code mode.

exception `segno.MaskError`

Indicates errors related to QR Code data mask.

exception `segno.VersionError`

Indicates errors related to the QR Code version.

exception `segno.DataOverflowError`

Indicates a problem that the provided data does not fit into the provided QR Code version or the data is too large in general.

class `segno.QRCode` (*code*)

Represents a (Micro) QR Code.

matrix_iter (*scale=1, border=None*)

Returns an iterator over the matrix which includes the border.

The border is returned as sequence of light modules. Dark modules are reported as 0x1, light modules have the value 0x0.

The following example converts the QR Code matrix into a list of lists which use boolean values for the modules (True = dark module, False = light module):

```
>>> import segno
>>> qr = segno.make('The Beatles')
>>> size = qr.symbol_size()[0]
>>> res = []
>>> # Scaling factor 2, default border
>>> for row in qr.matrix_iter(scale=2):
>>>     res.append([col == 0x1 for col in row])
```

```
>>> size * 2 == len(res[0])
True
```

Parameters

- **scale** (*int*) – The scaling factor (default: 1).
- **border** (*int*) – The size of border / quiet zone or `None` to indicate the default border.

Raises `ValueError` if the scaling factor or the border is invalid (i.e. negative).

png_data_uri (**kw)

Converts the QR Code into a PNG data URI.

Uses the same keyword parameters as the usual PNG serializer.

Return type `str`

save (out, kind=`None`, **kw)

Serializes the QR Code in one of the supported formats. The serialization format depends on the filename extension.

Common keywords

Name	Description
scale	Integer or float indicating the size of a single module. Default: 1. The interpretation of the scaling factor depends on the serializer. For pixel-based output (like PNG) the scaling factor is interpreted as pixel-size (1 = 1 pixel). EPS interprets 1 as 1 point (1/72 inch) per module. Some serializers (like SVG) accept float values. If the serializer does not accept float values, the value will be converted to an integer value (note: <code>int(1.6) == 1</code>).
border	Integer indicating the size of the quiet zone. If set to <code>None</code> (default), the recommended border size will be used (4 for QR Codes, 2 for a Micro QR Codes).
color	A string or tuple representing a color value for the dark modules. The default value is “black”. The color can be provided as (R, G, B) tuple, as web color name (like “red”) or in hexadecimal format (#RGB or #RRGGBB). Some serializers (SVG and PNG) accept an alpha transparency value like #RRGGBBAA.
background	A string or tuple representing a color for the light modules or background. See “color” for valid values. The default value depends on the serializer. SVG uses no background color (<code>None</code>) by default, other serializers use “white” as default background color.

Scalable Vector Graphics (SVG)

Name	Description
kind	“svg” or “svgz” (to create a gzip compressed SVG)
scale	integer or float
color	Default: “#000” (black) <code>None</code> is a valid value. If set to <code>None</code> , the resulting path won’t have a “stroke” attribute. The “stroke” attribute may be defined via CSS (external). If an alpha channel is defined, the output depends of the used SVG version. For SVG versions ≥ 2.0 , the “stroke” attribute will have a value like “rgba(R, G, B, A)”, otherwise the path gets another attribute “stroke-opacity” to emulate the alpha channel. To minimize the document size, the SVG serializer uses automatically the shortest color representation: If a value like “#000000” is provided, the resulting document will have a color value of “#000”. If the color is “#FF0000”, the resulting color is not “#F00”, but the web color name “red”.
back-ground	Default value <code>None</code> . If this paramater is set to another value, the resulting image will have another path which is used to define the background color. If an alpha channel is used, the resulting path may have a “fill-opacity” attribute (for SVG version < 2.0) or the “fill” attribute has a “rgba(R, G, B, A)” value. See keyword “color” for further details.
xmldecl	Boolean value (default: <code>True</code>) indicating whether the document should have an XML declaration header. Set to <code>False</code> to omit the header.
svgns	Boolean value (default: <code>True</code>) indicating whether the document should have an explicit SVG namespace declaration. Set to <code>False</code> to omit the namespace declaration. The latter might be useful if the document should be embedded into a HTML 5 document where the SVG namespace is implicitly defined.
title	String (default: <code>None</code>) Optional title of the generated SVG document.
desc	String (default: <code>None</code>) Optional description of the generated SVG document.
svgid	A string indicating the ID of the SVG document (if set to <code>None</code> (default), the SVG element won’t have an ID).
svg-class	Default: “segno”. The CSS class of the SVG document (if set to <code>None</code> , the SVG element won’t have a class).
lineclass	Default: “qrline”. The CSS class of the path element (which draws the dark modules (if set to <code>None</code> , the path won’t have a class).
omit-size	Indicates if width and height attributes should be omitted (default: <code>False</code>). If these attributes are omitted, a <code>viewBox</code> attribute will be added to the document.
unit	Default: <code>None</code> Inidctaes the unit for width / height and other coordinates. By default, the unit is unspecified and all values are in the user space. Valid values: em, ex, px, pt, pc, cm, mm, in, and percentages (any string is accepted, this parameter is not validated by the serializer)
encod-ing	Encoding of the XML document. “utf-8” by default.
svgver-sion	SVG version (default: <code>None</code>). If specified (a float), the resulting document has an explicit “version” attribute. If set to <code>None</code> , the document won’t have a “version” attribute. This parameter is not validated.
com-presslevel	Default: 9. This parameter is only valid, if a compressed SVG document should be created (file extension “svgz”). 1 is fastest and produces the least compression, 9 is slowest and produces the most. 0 is no compression.

Portable Network Graphics (PNG)

Name	Description
kind	“png”
scale	integer
color	Default: “#000” (black) <code>None</code> is a valid value iff background is not <code>None</code> .
background	Default value <code>#fff</code> (white) See keyword “color” for further details.
compressionlevel	Default: 9. Integer indicating the compression level for the <code>IDAT</code> (data) chunk. 1 is fastest and produces the least compression, 9 is slowest and produces the most. 0 is no compression.
dpi	Default: <code>None</code> . Specifies the DPI value for the image. By default, the DPI value is unspecified. Please note that the DPI value is converted into meters (maybe with rounding errors) since PNG does not support the unit “dots per inch”.
addad	Boolean value (default: <code>True</code>) to (dis-)allow a “Software” comment indicating that the file was created by Segno.

Encapsulated PostScript (EPS)

Name	Description
kind	“eps”
scale	integer or float
color	Default: “#000” (black)
background	Default value: <code>None</code> (no background)

Portable Document Format (PDF)

Name	Description
kind	“pdf”
scale	integer or float
compressionlevel	Default: 9. Integer indicating the compression level. 1 is fastest and produces the least compression, 9 is slowest and produces the most. 0 is no compression.

Text (TXT)

Does not support the “scale” keyword!

Name	Description
kind	“txt”
color	Default: “1”
background	Default: “0”

ANSI escape code

Supports the “border” keyword, only!

Name	Description
kind	“ans”

Portable Bitmap (PBM)

Name	Description
kind	“pbm”
scale	integer
plain	Default: <code>False</code> . Boolean to switch between the P4 and P1 format. If set to <code>True</code> , the (outdated) P1 serialization format is used.

Portable Arbitrary Map (PAM)

Name	Description
kind	“pam”
scale	integer
color	Default: “#000” (black).
background	Default value #fff (white). Use <code>None</code> for a transparent background.

LaTeX / PGF/TikZ

Name	Description
kind	“tex”
scale	integer or float
color	LaTeX color name (default: “black”). The color is written “at it is”, so ensure that the color is a standard color or it has been defined in the enclosing LaTeX document.
url	Default: <code>None</code> . Optional URL where the QR Code should point to. Requires the <code>hyperref</code> package.

X BitMap (XBM)

Name	Description
kind	“xbm”
scale	integer
name	Name of the variable (default: “img”)

X PixMap (XPM)

Name	Description
kind	“xpm”
scale	integer
color	Default: “#000” (black).
background	Default value #fff (white) <code>None</code> indicates a transparent background.
name	Name of the variable (default: “img”)

Parameters

- **out** – A filename or a writable file-like object with a `name` attribute. Use the `kind` parameter if `out` is a `io.ByteIO` or `io.StringIO` stream which don’t have a `name` attribute.
- **kind** – If the desired output format cannot be determined from the `out` parameter, this parameter can be used to indicate the serialization format (i.e. “svg” to enforce SVG output)
- **kw** – Any of the supported keywords by the specific serialization method.

show (`delete_after=20, scale=10, border=None, color=u'#000', background=u'fff'`)

Displays this QR code.

This method is mainly intended for debugging purposes.

This method saves the output of the `png()` method (by default with a scaling factor of 10) to a temporary file and opens it with the standard PNG viewer application or within the standard webbrowser. The temporary file is deleted afterwards (unless `delete_after` is set to `None`).

If this method does not show any result, try to increase the `delete_after` value or set it to `None`

Parameters `delete_after` – Time in seconds to wait till the temporary file is deleted.

svg_data_uri (`xmldecl=False, encode_minimal=False, omit_charset=False, nl=False, **kw`)

Converts the QR Code into a SVG data URI.

The XML declaration is omitted by default (set `xmldecl` to `True` to enable it), further the newline is omitted by default (set `nl` to `True` to enable it).

Aside from the missing `out` parameter and the different `xmldecl` and `nl` default values and the additional parameter `encode_minimal` and `omit_charset` this method uses the same parameters as the usual SVG serializer.

Parameters

- **xmldecl** (*bool*) – Indicates if the XML declaration should be serialized (default: `False`)
- **encode_minimal** (*bool*) – Indicates if the resulting data URI should use minimal percent encoding (disabled by default).
- **omit_charset** (*bool*) – Indicates if the `; charset=...` should be omitted (disabled by default)

Return type `str`

symbol_size (*scale=1, border=None*)

Returns the symbol size (width x height) with the provided border and scaling factor.

Parameters

- **scale** (*int or float*) – Indicates the size of a single module (default: `1`). The size of a module depends on the used output format; i.e. in a PNG context, a scaling factor of `2` indicates that a module has a size of `2 x 2` pixel. Some outputs (i.e. SVG) accept floating point values.
- **border** (*int*) – The border size or `None` to specify the default quiet zone (`4` for QR Codes, `2` for Micro QR Codes).

Return type `tuple` (width, height)

terminal (*out=None, border=None*)

Serializes the matrix as ANSI escape code.

Parameters

- **out** – Filename or a file-like object supporting to write text. If `None` (default), the matrix is written to `sys.stdout`.
- **border** (*int*) – Integer indicating the size of the quiet zone. If set to `None` (default), the recommended border size will be used (`4` for QR Codes, `2` for a Micro QR Codes).

default_border_size

Indicates the default border size aka quiet zone.

designator

Returns the version and error correction level as string `V-E` where `V` represents the version number and `E` the error level.

error

Error correction level; either a string (`"L"`, `"M"`, `"Q"`, `"H"`) or `None` if the QR Code provides no error correction (Micro QR Code version M1)

is_micro

Indicates if this QR Code is a Micro QR Code

mask = None

Returns the data mask pattern reference (an integer).

matrix = None

Returns the matrix (tuple of bytearrays).

mode

String indicating the mode (“numeric”, “alphanumeric”, “byte”, “kanji”). May be `None` if multiple modes are used.

version

(Micro) QR Code version. Either a string (“M1”, “M2”, “M3”, “M4”) or an integer in the range of 1 .. 40.

`segno.make` (*content*, *error=None*, *version=None*, *mode=None*, *mask=None*, *encoding=None*, *eci=False*, *micro=None*, *boost_error=True*)
Creates a (Micro) QR Code.

This is main entry point to create QR Codes and Micro QR Codes.

Aside from *content*, all parameters are optional and an optimal (minimal) (Micro) QR Code with a maximal error correction level (minimum “M”) is generated.

Parameters

- **content** (*str*, *int*, *bytes*) – The data to encode. Either a Unicode string, an integer or bytes. If bytes are provided, the *encoding* parameter should be used to specify the used encoding.
- **error** (*str*, *unicode* or *None*) – Error correction level. If `None` (default), error correction level L is used (note: Micro QR Code version M1 does not support error correction. If an explicit error level is used, a M1 QR Code won’t be generated). Valid values: `None` (allowing generation of M1 codes or use error correction level “L” or better see *boost_error*), “L”, “M”, “Q”, “H” (error correction level “H” isn’t available for Micro QR Codes).

Error correction level	Error correction capability
L (Segno’s default unless version M1)	recovers 7% of data
M	recovers 15% of data
Q	recovers 25% of data
H (not available for Micro QR Codes)	recovers 30% of data

Higher error levels may require larger QR Codes (see also *version* parameter).

The *error* parameter is case insensitive.

See also the *boost_error* parameter.

- **version** (*int*, *str*, *unicode* or *None*.) – QR Code version. If the value is `None` (default), the minimal version which fits for the input data will be used. Valid values: “M1”, “M2”, “M3”, “M4” (for Micro QR Codes) or an integer between 1 and 40 (for QR Codes). The *version* parameter is case insensitive.
- **mode** (*str*, *unicode*, or *None*) – “numeric”, “alphanumeric”, “byte”, or “kanji”. If the value is `None` (default) the appropriate mode will automatically be determined. If *version* refers a to Micro QR Code, this function may raise a `ModeError` if the provided *mode* is not supported.

Mode	(Micro) QR Code Version
numeric	1 - 40, M1, M2, M3, M4
alphanumeric	1 - 40, M2, M3, M4
byte	1 - 40, M3, M4
kanji	1 - 40, M3, M4

The *mode* parameter is case insensitive.

- **mask** (*int* or *None*) – Data mask. If the value is `None` (default), the appropriate data mask is chosen automatically. If the *mask* parameter is provided, this function may raise a `MaskError` if the mask is invalid.

- **encoding** (*unicode/str/None*) – Indicates the encoding in mode “byte”. By default (*encoding* is *None*) the implementation tries to use the standard conform ISO/IEC 8859-1 encoding and if it does not fit, it will use UTF-8. Note that no ECI mode indicator is inserted by default (see *eci*). The *encoding* parameter is case insensitive.
- **eci** (*bool*) – Indicates if binary data which does not use the default encoding (ISO/IEC 8859-1) should enforce the ECI mode. Since a lot of QR Code readers do not support the ECI mode, this feature is disabled by default and the data is encoded in the provided *encoding* using the usual “byte” mode. Set *eci* to *True* if an ECI header should be inserted into the QR Code. Note that the implementation may not know the ECI designator for the provided *encoding* and may raise an exception if the ECI designator cannot be found. The ECI mode is not supported by Micro QR Codes.
- **micro** (*bool or None*) – If *version* is *None* this parameter can be used to allow the creation of a Micro QR Code. If set to *False*, a QR Code is generated. If set to *None* (default) a Micro QR Code may be generated if applicable. If set to *True* the algorithm generates a Micro QR Code or raises an exception if the *mode* is not compatible or the *content* is too large for Micro QR Codes.
- **boost_error** (*bool*) – Indicates if the error correction level may be increased if it does not affect the version (default: *True*). If set to *True*, the *error* parameter is interpreted as minimum error level. If set to *False*, the resulting (Micro) QR Code uses the provided error level (or the default error correction level, if error is *None*)

Raises *QRCodeError*: In case of a problem. In fact, it’s more likely that a derived exception is thrown: *ModeError*: In case of problems with the mode (i.e. invalid mode or invalid *mode* / *version* combination. *VersionError*: In case the *version* is invalid or the *micro* parameter contradicts the provided *version*. *ErrorLevelError*: In case the error level is invalid or the error level is not supported by the provided *version*. *DataOverflowError*: In case the data does not fit into a (Micro) QR Code or it does not fit into the provided *version*. *MaskError*: In case an invalid data mask was specified.

Return type *QRCode*

`segno.make_qr` (*content*, *error=None*, *version=None*, *mode=None*, *mask=None*, *encoding=None*, *eci=False*, *boost_error=True*)
Creates a QR Code (never a Micro QR Code).

See *make ()* for a description of the parameters.

Return type *QRCode*

`segno.make_micro` (*content*, *error=None*, *version=None*, *mode=None*, *mask=None*, *encoding=None*, *boost_error=True*)
Creates a Micro QR Code.

See *make ()* for a description of the parameters.

Note: Error correction level “H” isn’t available for Micro QR Codes. If used, this function raises a *segno.ErrorLevelError*.

Return type *QRCode*

9.2 High level QR Code factories

Additional factory functions for common QR Codes.

The factory functions which return a QR Code use the minimum error correction level “M”. To create a (Micro) QR Code which should use a specific error correction level or version etc., use the “_data” factory functions which return a string which can be used as input for `segno.make()`.

`segno.helpers.make_email(to, cc=None, bcc=None, subject=None, body=None)`

Encodes either a simple e-mail address or a complete message with (blind) carbon copies and a subject and a body.

Parameters

- **to** (*str/iterable*) – The email address (recipient). Multiple values are allowed.
- **cc** (*str/iterable/None*) – The carbon copy recipient. Multiple values are allowed.
- **bcc** (*str/iterable/None*) – The blind carbon copy recipient. Multiple values are allowed.
- **subject** (*str/None*) – The subject.
- **body** (*str/None*) – The message body.

`segno.helpers.make_geo(lat, lng)`

Returns a QR Code which encodes geographic location using the geo URI scheme.

Parameters

- **lat** (*float*) – Latitude
- **lng** (*float*) – Longitude

Return type *segno.QRCode*

`segno.helpers.make_geo_data(lat, lng)`

Creates a geo location URI.

Parameters

- **lat** (*float*) – Latitude
- **lng** (*float*) – Longitude

Return type *str*

`segno.helpers.make_email_data(to, cc=None, bcc=None, subject=None, body=None)`

Creates either a simple “mailto:” URL or complete e-mail message with (blind) carbon copies and a subject and a body.

Parameters

- **to** (*str/iterable*) – The email address (recipient). Multiple values are allowed.
- **cc** (*str/iterable/None*) – The carbon copy recipient. Multiple values are allowed.
- **bcc** (*str/iterable/None*) – The blind carbon copy recipient. Multiple values are allowed.
- **subject** (*str/None*) – The subject.
- **body** (*str/None*) – The message body.

`segno.helpers.make_mecard(name, reading=None, email=None, phone=None, videophone=None, memo=None, nickname=None, birthday=None, url=None, pobox=None, roomno=None, houseno=None, city=None, prefecture=None, zipcode=None, country=None)`

Returns a QR Code which encodes a [MeCard](#)

Parameters

- **name** (*str*) – Name. If it contains a comma, the first part is treated as lastname and the second part is treated as forename.
- **reading** (*str/None*) – Designates a text string to be set as the kana name in the phone-book
- **email** (*str/iterable*) – E-mail address. Multiple values are allowed.
- **phone** (*str/iterable*) – Phone number. Multiple values are allowed.
- **videophone** (*str/iterable*) – Phone number for video calls. Multiple values are allowed.
- **memo** (*str*) – A notice for the contact.
- **nickname** (*str*) – Nickname.
- **birthday** (*str/int/date*) – Birthday. If a string is provided, it should encode the date as YYYYMMDD value.
- **url** (*str/iterable*) – Homepage. Multiple values are allowed.
- **pobox** (*str/None*) – P.O. box (address information).
- **roomno** (*str/None*) – Room number (address information).
- **hougeno** (*str/None*) – House number (address information).
- **city** (*str/None*) – City (address information).
- **prefecture** (*str/None*) – Prefecture (address information).
- **zipcode** (*str/None*) – Zip code (address information).
- **country** (*str/None*) – Country (address information).

Return type *segno.QRCode*

`segno.helpers.make_mecard_data` (*name*, *reading=None*, *email=None*, *phone=None*, *videophone=None*, *memo=None*, *nickname=None*, *birthday=None*, *url=None*, *pobox=None*, *roomno=None*, *hougeno=None*, *city=None*, *prefecture=None*, *zipcode=None*, *country=None*)

Creates a string encoding the contact information as MeCard.

Parameters

- **name** (*str*) – Name. If it contains a comma, the first part is treated as lastname and the second part is treated as forename.
- **reading** (*str/None*) – Designates a text string to be set as the kana name in the phone-book
- **email** (*str/iterable*) – E-mail address. Multiple values are allowed.
- **phone** (*str/iterable*) – Phone number. Multiple values are allowed.
- **videophone** (*str/iterable*) – Phone number for video calls. Multiple values are allowed.
- **memo** (*str*) – A notice for the contact.
- **nickname** (*str*) – Nickname.
- **birthday** (*(str/int/date)*) – Birthday. If a string is provided, it should encode the date as YYYYMMDD value.
- **url** (*str/iterable*) – Homepage. Multiple values are allowed.

- **pobox** (*str/None*) – P.O. box (address information).
- **roomno** (*str/None*) – Room number (address information).
- **housetno** (*str/None*) – House number (address information).
- **city** (*str/None*) – City (address information).
- **prefecture** (*str/None*) – Prefecture (address information).
- **zipcode** (*str/None*) – Zip code (address information).
- **country** (*str/None*) – Country (address information).

Return type `str`

`segno.helpers.make_vcard`(*name, displayname, email=None, phone=None, fax=None, videophone=None, memo=None, nickname=None, birthday=None, url=None, pobox=None, street=None, city=None, region=None, zipcode=None, country=None, org=None, lat=None, lng=None, source=None, rev=None*)

Creates a QR Code which encodes a vCard version 3.0.

Only a subset of available vCard properties is supported.

Parameters

- **name** (*str*) – The name. If it contains a semicolon, , the first part is treated as lastname and the second part is treated as forename.
- **displayname** (*str*) – Common name.
- **email** (*str/iterable*) – E-mail address. Multiple values are allowed.
- **phone** (*str/iterable*) – Phone number. Multiple values are allowed.
- **fax** (*str/iterable*) – Fax number. Multiple values are allowed.
- **videophone** (*str/iterable*) – Phone number for video calls. Multiple values are allowed.
- **memo** (*str*) – A notice for the contact.
- **nickname** (*str*) – Nickname.
- **birthday** (*str/date*) – Birthday. If a string is provided, it should encode the date as YYYY-MM-DD value.
- **url** (*str/iterable*) – Homepage. Multiple values are allowed.
- **pobox** (*str/None*) – P.O. box (address information).
- **street** (*str/None*) – Street address.
- **city** (*str/None*) – City (address information).
- **region** (*str/None*) – Region (address information).
- **zipcode** (*str/None*) – Zip code (address information).
- **country** (*str/None*) – Country (address information).
- **org** (*str*) – Company / organization name.
- **lat** (*float*) – Latitude.
- **lng** (*float*) – Longitude.
- **source** (*str*) – URL where to obtain the vCard.

- **rev** (*str/date*) – Revision of the vCard / last modification date.

Return type *segno.QRCode*

`segno.helpers.make_vcard_data` (*name, displayname, email=None, phone=None, fax=None, videophone=None, memo=None, nickname=None, birthday=None, url=None, pobox=None, street=None, city=None, region=None, zipcode=None, country=None, org=None, lat=None, lng=None, source=None, rev=None*)

Creates a string encoding the contact information as vCard 3.0.

Only a subset of available vCard properties is supported.

Parameters

- **name** (*str*) – The name. If it contains a semicolon, , the first part is treated as lastname and the second part is treated as forename.
- **displayname** (*str*) – Common name.
- **email** (*str/iterable*) – E-mail address. Multiple values are allowed.
- **phone** (*str/iterable*) – Phone number. Multiple values are allowed.
- **fax** (*str/iterable*) – Fax number. Multiple values are allowed.
- **videophone** (*str/iterable*) – Phone number for video calls. Multiple values are allowed.
- **memo** (*str*) – A notice for the contact.
- **nickname** (*str*) – Nickname.
- **birthday** (*str/date*) – Birthday. If a string is provided, it should encode the date as YYYY-MM-DD value.
- **url** (*str/iterable*) – Homepage. Multiple values are allowed.
- **pobox** (*str/None*) – P.O. box (address information).
- **street** (*str/None*) – Street address.
- **city** (*str/None*) – City (address information).
- **region** (*str/None*) – Region (address information).
- **zipcode** (*str/None*) – Zip code (address information).
- **country** (*str/None*) – Country (address information).
- **org** (*str*) – Company / organization name.
- **lat** (*float*) – Latitude.
- **lng** (*float*) – Longitude.
- **source** (*str*) – URL where to obtain the vCard.
- **rev** (*str/date*) – Revision of the vCard / last modification date.

Return type *str*

`segno.helpers.make_wifi` (*ssid, password, security, hidden=False*)

Creates a WIFI configuration QR Code.

Parameters

- **ssid** (*str*) – The SSID of the network.

- **password** (*str/None*) – The password.
- **security** (*str/None*) – Authentication type; the value should be “WEP” or “WPA”. Set to `None` to omit the value. “nopass” is equivalent to setting the value to `None` but in the former case, the value is not omitted.
- **hidden** (*bool*) – Indicates if the network is hidden (default: `False`)

Return type *segno.QRCode*

`segno.helpers.make_wifi_data(ssid, password, security, hidden=False)`
Creates WIFI configuration string.

Parameters

- **ssid** (*str*) – The SSID of the network.
- **password** (*str/None*) – The password.
- **security** (*str/None*) – Authentication type; the value should be “WEP” or “WPA”. Set to `None` to omit the value. “nopass” is equivalent to setting the value to `None` but in the former case, the value is not omitted.
- **hidden** (*bool*) – Indicates if the network is hidden (default: `False`)

Return type *str*

Segno's low level API

`segno.make()`, `segno.make_qr()`, and `segno.make_micro()` return a `segno.QRCode` which implements almost no logic but uses the result of `segno.encoder.encode()` glued together with the functionality of `segno.writers` to provide a simple (supposed to be user-friendly) API.

A completely different API is possible by utilizing `segno.encoder.encode()` which returns just a tuple: (matrix, version, error, mask, segments). The module `segno.writers` is independent of the `segno.encoder` module and vice versa.

10.1 segno.encoder

QR Code and Micro QR Code encoder.

“QR Code” and “Micro QR Code” are registered trademarks of DENSO WAVE INCORPORATED.

exception `segno.encoder.QRCodeError`

Generic QR Code error.

exception `segno.encoder.VersionError`

Indicates errors related to the QR Code version.

exception `segno.encoder.ModeError`

Indicates errors related to QR Code mode.

exception `segno.encoder.ErrorLevelError`

Indicates errors related to QR Code error correction level.

exception `segno.encoder.MaskError`

Indicates errors related to QR Code data mask.

exception `segno.encoder.DataOverflowError`

Indicates a problem that the provided data does not fit into the provided QR Code version or the data is too large in general.

`segno.encoder.encode` (*content*, *error=None*, *version=None*, *mode=None*, *mask=None*, *encoding=None*, *eci=False*, *micro=None*, *boost_error=True*)

Creates a (Micro) QR Code.

See `segno.make()` for a detailed description of the parameters.

Contrary to `make` this function returns a named tuple: (matrix, version, error, mask, segments)

Note that `version` is always an integer referring to the values of the `segno.consts` constants. `error` is `None` iff a M1 QR Code was generated, otherwise it is always an integer.

Return type namedtuple

10.2 segno.writers

Standard serializers and utility functions for serializers.

The serializers are independent of the `segno.QRCode` (and the `segno.encoder.Code`) class; they just need a matrix (tuple of bytearray) and the version constant.

`segno.writers.as_png_data_uri` (*matrix*, *version*, *scale=1*, *border=None*, *color=u'#000'*, *background=u'fff'*, *compresslevel=9*, *addad=True*)

Converts the provided matrix into a PNG data URI.

Return type str

`segno.writers.as_svg_data_uri` (*matrix*, *version*, *scale=1*, *border=None*, *color=u'#000'*, *background=None*, *xmldecl=False*, *svgs=True*, *title=None*, *desc=None*, *svgid=None*, *svgclass=u'segno'*, *lineclass=u'qrline'*, *omitsize=False*, *unit=u''*, *encoding=u'utf-8'*, *svgversion=None*, *nl=False*, *encode_minimal=False*, *omit_charset=False*)

Converts the matrix to a SVG data URI.

The XML declaration is omitted by default (set `xmldecl` to `True` to enable it), further the newline is omitted by default (set `nl` to `True` to enable it).

Aside from the missing `out` parameter and the different `xmldecl` and `nl` default values and the additional parameter `encode_minimal` and `omit_charset` this function uses the same parameters as the usual SVG serializer.

Parameters

- **encode_minimal** (*bool*) – Indicates if the resulting data URI should use minimal percent encoding (disabled by default).
- **omit_charset** (*bool*) – Indicates if the `; charset=...` should be omitted (disabled by default)

Return type str

`segno.writers.save` (*matrix*, *version*, *out*, *kind=None*, ***kw*)

Serializes the matrix in any of the supported formats.

Parameters

- **matrix** – The matrix to serialize.
- **version** (*int*) – The (Micro) QR code version
- **out** – A filename or a writable file-like object with a `name` attribute. If a stream like `io.ByteIO` or `io.StringIO` object without a `name` attribute is provided, use the `kind` parameter to specify the serialization format.
- **kind** – If the desired output format cannot be extracted from the filename, this parameter can be used to indicate the serialization format (i.e. “svg” to enforce SVG output)
- **kw** – Any of the supported keywords by the specific serialization method.

`segno.writers.writable` (**args*, ***kws*)

Returns a writable file-like object.

Usage:

```
with writable(file_name_or_path, 'wb') as f:
    ...
```

Parameters

- **file_or_path** – Either a file-like object or a filename.
- **mode** (*str*) – String indicating the writing mode (i.e. 'wb')

`segno.writers.write_eps(matrix, version, out, scale=1, border=None, color=u'#000', background=None)`
Serializes the QR Code as EPS document.

Parameters

- **matrix** – The matrix to serialize.
- **version** (*int*) – The (Micro) QR code version
- **out** – Filename or a file-like object supporting to write strings.
- **scale** – Indicates the size of a single module (default: 1 which corresponds to 1 point (1/72 inch) per module).
- **border** (*int*) – Integer indicating the size of the quiet zone. If set to `None` (default), the recommended border size will be used (4 for QR Codes, 2 for a Micro QR Codes).
- **color** – Color of the modules (default: black). The color can be provided as (R, G, B) tuple (this method accepts floats as R, G, B values), as web color name (like “red”) or in hexadecimal format (#RGB or #RRGGBB).
- **background** – Optional background color (default: `None` = no background color). See *color* for valid values.

`segno.writers.write_pam(matrix, version, out, scale=1, border=None, color=u'#000', background=u'fff')`
Serializes the matrix as PAM image.

Parameters

- **matrix** – The matrix to serialize.
- **version** (*int*) – The (Micro) QR code version
- **out** – Filename or a file-like object supporting to write binary data.
- **scale** – Indicates the size of a single module (default: 1 which corresponds to 1 x 1 pixel per module).
- **border** (*int*) – Integer indicating the size of the quiet zone. If set to `None` (default), the recommended border size will be used (4 for QR Codes, 2 for a Micro QR Codes).
- **color** – Color of the modules (default: black). The color can be provided as (R, G, B) tuple, as web color name (like “red”) or in hexadecimal format (#RGB or #RRGGBB).
- **background** – Optional background color (default: white). See *color* for valid values. In addition, `None` is accepted which indicates a transparent background.

`segno.writers.write_pbm(matrix, version, out, scale=1, border=None, plain=False)`
Serializes the matrix as PBM image.

Parameters

- **matrix** – The matrix to serialize.

- **version** (*int*) – The (Micro) QR code version
- **out** – Filename or a file-like object supporting to write binary data.
- **scale** – Indicates the size of a single module (default: 1 which corresponds to 1 x 1 pixel per module).
- **border** (*int*) – Integer indicating the size of the quiet zone. If set to `None` (default), the recommended border size will be used (4 for QR Codes, 2 for a Micro QR Codes).
- **plain** (*bool*) – Indicates if a P1 (ASCII encoding) image should be created (default: `False`). By default a (binary) P4 image is created.

`segno.writers.write_pdf(matrix, version, out, scale=1, border=None, compresslevel=9)`
Serializes the QR Code as PDF document.

Parameters

- **matrix** – The matrix to serialize.
- **version** (*int*) – The (Micro) QR code version
- **out** – Filename or a file-like object supporting to write bytes.
- **scale** – Indicates the size of a single module (default: 1 which corresponds to 1 x 1 pixel per module).
- **border** (*int*) – Integer indicating the size of the quiet zone. If set to `None` (default), the recommended border size will be used (4 for QR Codes, 2 for a Micro QR Codes).
- **compresslevel** (*int*) – Integer indicating the compression level (default: 9). 1 is fastest and produces the least compression, 9 is slowest and produces the most. 0 is no compression.

`segno.writers.write_png(matrix, version, out, scale=1, border=None, color=u'#000', background=u'#fff', compresslevel=9, dpi=None, addad=True)`
Serializes the QR Code as PNG image.

By default, the generated PNG will be a greyscale image with a bitdepth of 1. If different colors are provided, an indexed-color image with the same bitdepth is generated.

Parameters

- **matrix** – The matrix to serialize.
- **version** (*int*) – The (Micro) QR code version
- **out** – Filename or a file-like object supporting to write bytes.
- **scale** – Indicates the size of a single module (default: 1 which corresponds to 1 x 1 pixel per module).
- **border** (*int*) – Integer indicating the size of the quiet zone. If set to `None` (default), the recommended border size will be used (4 for QR Codes, 2 for a Micro QR Codes).
- **color** – Color of the modules (default: black). The color can be provided as (R, G, B) tuple, as web color name (like “red”) or in hexadecimal format (#RGB or #RRGGBB).
- **background** – Optional background color (default: white). See *color* for valid values. In addition, `None` is accepted which indicates a transparent background.
- **dpi** (*int*) – Optional DPI setting. By default (`None`), the PNG won’t have any DPI information. Note that the DPI value is converted into meters since PNG does not support any DPI information.
- **compresslevel** (*int*) – Integer indicating the compression level (default: 9). 1 is fastest and produces the least compression, 9 is slowest and produces the most. 0 is no compression.

```
segno.writers.write_svg(matrix, version, out, scale=1, border=None, color=u'#000', back-
                        ground=None, xmldecl=True, svgnns=True, title=None, desc=None,
                        svgid=None, svgclass=u'segno', lineclass=u'qrline', omitsize=False,
                        unit=None, encoding=u'utf-8', svgversion=None, nl=True)
```

Serializes the QR Code as SVG document.

Parameters

- **matrix** – The matrix to serialize.
- **version** (*int*) – The (Micro) QR code version
- **out** – Filename or a file-like object supporting to write bytes.
- **scale** – Indicates the size of a single module (default: 1 which corresponds to 1 x 1 pixel per module).
- **border** (*int*) – Integer indicating the size of the quiet zone. If set to `None` (default), the recommended border size will be used (4 for QR Codes, 2 for a Micro QR Codes).
- **color** – Color of the modules (default: #000). Any value which is supported by SVG can be used. In addition, `None` is a valid value. The resulting path won't have a `stroke` attribute.
- **background** – Optional background color (default: `None` = no background color). See *color* for valid values.
- **xmldecl** (*bool*) – Indicates if the XML declaration header should be written (default: `True`)
- **svgnns** (*bool*) – Indicates if the SVG namespace should be written (default: `True`).
- **title** (*str*) – Optional title of the generated SVG document.
- **desc** (*str*) – Optional description of the generated SVG document.
- **svgid** – The ID of the SVG document (if set to `None` (default), the SVG element won't have an ID).
- **svgclass** – The CSS class of the SVG document (if set to `None`, the SVG element won't have a class).
- **lineclass** – The CSS class of the path element (which draws the “black” modules (if set to `None`, the path won't have a class).
- **omitsize** (*bool*) – Indicates if width and height attributes should be omitted (default: `False`). If these attributes are omitted, a `viewBox` attribute will be added to the document.
- **unit** (*str*) – Unit for width / height and other coordinates. By default, the unit is unspecified and all values are in the user space. Valid values: `em`, `ex`, `px`, `pt`, `pc`, `cm`, `mm`, `in`, and percentages
- **encoding** (*str*) – Encoding of the XML document. “utf-8” by default.
- **svgversion** (*float*) – SVG version (default: `None`)
- **nl** (*bool*) – Indicates if the document should have a trailing newline (default: `True`)

```
segno.writers.write_svg_debug(matrix, version, out, scale=15, border=None,
                              fallback_color=u'fuchsia', color_mapping=None,
                              add_legend=True)
```

Internal SVG serializer which is useful to debugging purposes.

This function is not exposed to the `QRCode` class by intention and the resulting SVG document is very inefficient (lots of `<rect/>s`). Dark modules are black and light modules are white by default. Provide a custom `color_mapping` to override these defaults. Unknown modules are red by default.

Parameters

- **matrix** – The matrix
- **version** – Version constant
- **out** – binary file-like object or file name
- **scale** – Scaling factor
- **border** – Quiet zone
- **fallback_color** – Color which is used for modules which are not 0x0 or 0x1 and for which no entry in `color_mapping` is defined.
- **color_mapping** – dict of module values to color mapping (optional)
- **add_legend** (*bool*) – Indicates if the bit values should be added to the matrix (default: True)

`segno.writers.write_terminal` (*matrix, version, out, border=None*)

Function to write to a terminal which supports ANSI escape codes.

Parameters

- **matrix** – The matrix to serialize.
- **version** (*int*) – The (Micro) QR code version.
- **out** – Filename or a file-like object supporting to write text.
- **border** (*int*) – Integer indicating the size of the quiet zone. If set to `None` (default), the recommended border size will be used (4 for QR Codes, 2 for a Micro QR Codes).

`segno.writers.write_terminal_win` (*matrix, version, border=None*)

Function to write a QR Code to a MS Windows terminal.

Parameters

- **matrix** – The matrix to serialize.
- **version** (*int*) – The (Micro) QR code version
- **border** (*int*) – Integer indicating the size of the quiet zone. If set to `None` (default), the recommended border size will be used (4 for QR Codes, 2 for a Micro QR Codes).

`segno.writers.write_tex` (*matrix, version, out, scale=1, border=None, color=u'black', unit=u'pt', url=None*)

Serializes the matrix as LaTeX PGF picture.

Requires the [PGF/TikZ](#) package (i.e. `\usepackage{pgf}`) in the LaTeX source.

Parameters

- **matrix** – The matrix to serialize.
- **version** (*int*) – The (Micro) QR code version
- **out** – Filename or a file-like object supporting to write text data.
- **scale** – Indicates the size of a single module (default: 1 which corresponds to 1 x 1 in the provided unit per module).

- **border** (*int*) – Integer indicating the size of the quiet zone. If set to `None` (default), the recommended border size will be used (4 for QR Codes, 2 for a Micro QR Codes).
- **color** (*str*) – LaTeX color name. The color name is taken at it is, so ensure that it refers either to a default color name or that the color was defined previously.
- **unit** – Unit of the drawing (default: `pt`)
- **url** – Optional URL where the QR Code should point to. Requires the “hyperref” package. Default: `None`.

`segno.writers.write_txt` (*matrix, version, out, border=None, color=u'1', background=u'0'*)
Serializes QR code in a text format.

Parameters

- **matrix** – The matrix to serialize.
- **version** (*int*) – The (Micro) QR code version
- **out** – Filename or a file-like object supporting to write text.
- **border** (*int*) – Integer indicating the size of the quiet zone. If set to `None` (default), the recommended border size will be used (4 for QR Codes, 2 for a Micro QR Codes).
- **color** – Character to use for the black modules (default: `'1'`)
- **background** – Character to use for the white modules (default: `'0'`)

`segno.writers.write_xbm` (*matrix, version, out, scale=1, border=None, name=u'img'*)
Serializes the matrix as XBM image.

Parameters

- **matrix** – The matrix to serialize.
- **version** (*int*) – The (Micro) QR code version
- **out** – Filename or a file-like object supporting to write text data.
- **scale** – Indicates the size of a single module (default: 1 which corresponds to 1 x 1 in the provided unit per module).
- **border** (*int*) – Integer indicating the size of the quiet zone. If set to `None` (default), the recommended border size will be used (4 for QR Codes, 2 for a Micro QR Codes).
- **name** – Prefix for the variable names. Default: `“img”`. The prefix is used to construct the variable names: ``#define <prefix>_width' 'static unsigned char <prefix>_bits[]``

`segno.writers.write_xpm` (*matrix, version, out, scale=1, border=None, color=u'#000', background=u'fff', name=u'img'*)
Serializes the matrix as XPM image.

Parameters

- **matrix** – The matrix to serialize.
- **version** (*int*) – The (Micro) QR code version
- **out** – Filename or a file-like object supporting to write binary data.
- **scale** – Indicates the size of a single module (default: 1 which corresponds to 1 x 1 pixel per module).
- **border** (*int*) – Integer indicating the size of the quiet zone. If set to `None` (default), the recommended border size will be used (4 for QR Codes, 2 for a Micro QR Codes).

- **color** – Color of the modules (default: black). The color can be provided as (R, G, B) tuple, as web color name (like “red”) or in hexadecimal format (#RGB or #RRGGBB).
- **background** – Optional background color (default: white). See *color* for valid values. *None* indicates a transparent background.
- **name** (*str*) – Name of the image (must be a valid C-identifier). Default: “img”.

Indices and tables

- `genindex`
- `modindex`
- `search`

S

[segno](#), 21
[segno.encoder](#), 35
[segno.helpers](#), 28
[segno.writers](#), 36

A

as_png_data_uri() (in module segno.writers), 36
as_svg_data_uri() (in module segno.writers), 36

D

DataOverflowError, 21, 35
default_border_size (segno.QRCode attribute), 26
designator (segno.QRCode attribute), 26

E

encode() (in module segno.encoder), 35
error (segno.QRCode attribute), 26
ErrorLevelError, 21, 35

I

is_micro (segno.QRCode attribute), 26

M

make() (in module segno), 27
make_email() (in module segno.helpers), 29
make_geo() (in module segno.helpers), 29
make_geo_data() (in module segno.helpers), 29
make_make_email_data() (in module segno.helpers), 29
make_mecard() (in module segno.helpers), 29
make_mecard_data() (in module segno.helpers), 30
make_micro() (in module segno), 28
make_qr() (in module segno), 28
make_vcard() (in module segno.helpers), 31
make_vcard_data() (in module segno.helpers), 32
make_wifi() (in module segno.helpers), 32
make_wifi_data() (in module segno.helpers), 33
mask (segno.QRCode attribute), 26
MaskError, 21, 35
matrix (segno.QRCode attribute), 26
matrix_iter() (segno.QRCode method), 21
mode (segno.QRCode attribute), 26
ModeError, 21, 35

P

png_data_uri() (segno.QRCode method), 22

Q

QRCode (class in segno), 21
QRCodeError, 21, 35

S

save() (in module segno.writers), 36
save() (segno.QRCode method), 22
segno (module), 21
segno.encoder (module), 35
segno.helpers (module), 28
segno.writers (module), 36
show() (segno.QRCode method), 25
svg_data_uri() (segno.QRCode method), 25
symbol_size() (segno.QRCode method), 26

T

terminal() (segno.QRCode method), 26

V

version (segno.QRCode attribute), 27
VersionError, 21, 35

W

writable() (in module segno.writers), 36
write_eps() (in module segno.writers), 37
write_pam() (in module segno.writers), 37
write_pbm() (in module segno.writers), 37
write_pdf() (in module segno.writers), 38
write_png() (in module segno.writers), 38
write_svg() (in module segno.writers), 38
write_svg_debug() (in module segno.writers), 39
write_terminal() (in module segno.writers), 40
write_terminal_win() (in module segno.writers), 40
write_tex() (in module segno.writers), 40
write_txt() (in module segno.writers), 41
write_xbm() (in module segno.writers), 41
write_xpm() (in module segno.writers), 41